



# HALCON

a product of MVTec

## Installation Guide



## All about installing and licensing HALCON, Version 13.0.1

All rights reserved. No part of this publication may be reproduced, stored in a retrieval system, or transmitted in any form or by any means, electronic, mechanical, photocopying, recording, or otherwise, without prior written permission of the publisher.

Edition 1	December 2003	(HALCON 7.0)
Edition 1a	July 2004	(HALCON 7.0.1)
Edition 1b	April 2005	(HALCON 7.0.2)
Edition 2	July 2005	(HALCON 7.1)
Edition 2a	April 2006	(HALCON 7.1.1)
Edition 2b	December 2006	(HALCON 7.1.2)
Edition 3	June 2007	(HALCON 8.0)
Edition 3a	October 2007	(HALCON 8.0.1)
Edition 3b	April 2008	(HALCON 8.0.2)
Edition 4	December 2008	(HALCON 9.0)
Edition 4a	June 2009	(HALCON 9.0.1)
Edition 4b	March 2010	(HALCON 9.0.2)
Edition 5	October 2010	(HALCON 10.0)
Edition 5a	April 2011	(HALCON 10.0.1)
Edition 6	May 2012	(HALCON 11.0)
Edition 6a	November 2012	(HALCON 11.0.1)
Edition 6b	July 2013	(HALCON 11.0.2)
Edition 6c	April 2014	(HALCON 11.0.3)
Edition 6d	March 2015	(HALCON 11.0.4)
Edition 7	November 2014	(HALCON 12.0)
Edition 7a	July 2015	(HALCON 12.0.1)
Edition 7b	February 2016	(HALCON 12.0.2)
Edition 8	November 2016	(HALCON 13.0)
Edition 8a	June 2017	(HALCON 13.0.1)



Copyright © 2003-2017 by MVTec Software GmbH, München, Germany

Protected by the following patents: US 7,062,093, US 7,239,929, US 7,751,625, US 7,953,290, US 7,953,291, US 8,260,059, US 8,379,014, US 8,830,229. Further patents pending.

Microsoft, Windows, Windows Server 2008/2012, Windows 7/8/8.1/10, Microsoft .NET, Visual C++, Visual Basic, and ActiveX are either trademarks or registered trademarks of Microsoft Corporation.

AMD and AMD Athlon are either trademarks or registered trademarks of Advanced Micro Devices, Inc.

ARM is a registered trademark of ARM Limited.

Borland and Delphi are either trademarks or registered trademarks of Borland Software Corporation.

CodeMeter is a trademark of WIBU SYSTEMS AG.

Intel, and Pentium are either trademarks or registered trademarks of Intel Corporation.

Linux is a trademark of Linus Torvalds.

macOS and OpenCL are trademarks of Apple Inc.

OpenGL is a trademark of Silicon Graphics, Inc.

RedHat is a trademark of RedHat, Inc.

SuSE is a trademark of Novell, Inc.

Ubuntu is a trademark of Canonical Ltd..


All other nationally and internationally recognized trademarks and tradenames are hereby recognized.

More information about HALCON can be found at: <http://www.halcon.com/>

# About This Manual

The manual provides the necessary information to install HALCON and setup the licensing mechanism successfully. It is divided into the following chapters:

- **Introduction**  
A short overview of the different HALCON versions, available licensing schemes, and the system requirements.
- **Installing HALCON**  
How to install HALCON, either for the first time or in form of an update or upgrade.
- **All About HALCON Licenses**  
Detailed information about the different types of licenses and how to obtain and install them.
- **Troubleshooting**  
Possible problems and how to solve them.
- **Appendix**  
Details like the installed file structure and the relevant environment variables.

For **further information** about HALCON, please consult the Quick Guide, [section 1.5](#) on page 10,  which gives an overview of the available documentation.

## Notation

Except for Linux/macOS-specific sections, file paths and environment variables are printed in the Windows convention, e.g.,

```
%HALCONEXAMPLES%\extension_package\halconuser
```

to denote the subdirectory `halconuser` containing an example package within the HALCON examples directory referenced by the environment variable `HALCONEXAMPLES` (see [section A.2](#) on page 51 for more information on environment variables). The same expression in Linux/macOS convention would look like

```
$HALCONEXAMPLES/extension_package/halconuser
```



# Contents

<b>1</b>	<b>Introduction</b>	<b>7</b>
1.1	HALCON Configurations	7
1.2	Releases and HALCON Versions	8
1.3	Supported Platforms and System Requirements	9
1.4	Licensing	10
<b>2</b>	<b>Installing HALCON</b>	<b>13</b>
2.1	How to Obtain HALCON	13
2.2	Installing HALCON for the First Time	14
2.2.1	Windows	14
2.2.2	Linux	18
2.2.3	macOS	20
2.3	Installing Additional Parts of HALCON	21
2.4	Usage of the command <code>regsvr32</code> on Windows x64	21
2.5	Manual Runtime Installation	21
2.6	Updating HALCON	23
2.7	Upgrading HALCON	23
2.8	HALCON Installer Switches under Windows	23
2.9	Uninstalling HALCON	24
2.9.1	Windows	24
2.9.2	Linux	26
2.9.3	macOS	26
2.10	Managing Multiple HALCON Versions	27
2.11	Switching between Different HALCON Platform Versions under Windows	28
2.12	Installing HALCON Image Acquisition Interfaces	28
2.13	Installing HALCON Extension Packages	28
2.13.1	Using an Extension Package Within HDevelop	29
2.13.2	Using an Extension Package in a Stand-Alone Application	29
<b>3</b>	<b>All About HALCON Licenses</b>	<b>31</b>
3.1	What is a License?	31
3.2	Evaluation Licenses	33
3.3	Development Licenses	33
3.3.1	License Bound to a Network Card	34
3.3.2	License Bound to a Dongle	34

3.4	Runtime Licenses	34
3.5	How to Upgrade a License	36
<b>4</b>	<b>Troubleshooting</b>	<b>37</b>
4.1	Problems During Installation (Windows)	37
4.2	Problems During Uninstallation (Windows)	38
4.3	Problems Concerning Licenses	39
4.3.1	Extracting Host IDs	40
4.4	Troubleshooting in HDevelop or HALCON Applications	40
4.4.1	Startup Errors	40
<b>A</b>	<b>More on the Installation</b>	<b>43</b>
A.1	The Installed File Structure	43
A.1.1	Main Directory	43
A.1.2	Example Programs, Images, Models	49
A.1.3	Machine Configuration Data	50
A.1.4	User Configuration Data	50
A.2	HALCON's Environment Variables	51
A.2.1	Setting Environment Variables Under Windows	51
A.2.2	Setting Environment Variables Under Linux	51
A.2.3	HALCON-Specific Environment Variables	51
A.2.4	General Environment Variables	52
A.3	Registry Keys on Windows Systems	53
A.3.1	Registered File Types	53
A.3.2	Environment Variables	53
A.3.3	Basic Installation Data	54
A.3.4	Uninstall Information	54
A.3.5	HalconX	54
A.3.6	HDevEngineXLib	56
	<b>Index</b>	<b>59</b>

# Chapter 1

## Introduction

To use HALCON on a computer, you must

1. install HALCON on this computer and
2. obtain a license.

Before looking into the details of these two steps in [chapter 2](#) on page 13 and [chapter 3](#) on page 31, this chapter gives an overview of the different HALCON versions and licensing methods. Finally, it describes the system requirements for running HALCON.

### 1.1 HALCON Configurations

You can use HALCON in two configurations:

1. **Development version**

The development version (sometimes also denoted as full version) includes the full spectrum of HALCON, i.e., language interfaces to C, C++, .NET, and COM, interfaces to more than 50 frame grabbers, I/O device interfaces and hundreds of industrial cameras, the Extension Package Interface, which allows you to integrate your own HALCON operators, and, of course, the interactive development environment HDevelop. You need this version whenever you want to develop applications based on HALCON.

2. **Runtime version**

If you have finished developing an application based on HALCON, you only need a runtime version of HALCON for each computer where the application is to be run. Since the runtime version is not determined for developing applications it does not include the interactive development environment HDevelop. Furthermore, you can obtain runtime versions that include only parts of the functionality (so-called *modules*); please contact your local distributor for more information.

## 1.2 Releases and HALCON Versions

The term *version* has a second meaning: It denotes the major HALCON releases, e.g., HALCON 13.0 or HALCON 12.0, to differentiate them from so-called *maintenance releases* like HALCON 13.0.1. The main differences between these two types of releases are:

- **Functionality**

A new HALCON *version* always represents a major step in the functionality. This means that it contains a significant number of new operators, but possibly also new functionality in HDevelop, e.g., new assistants. Furthermore, the functionality of individual operators may be extended or operators have been sped up. Of course, all currently known bugs in the preceding release will have been fixed.

In contrast, the main intention of a *maintenance release* is to fix all currently known bugs. Nevertheless, such a release typically also brings some speed-ups and minor functional extensions.

- **Compatibility**

A new HALCON *version* is not downward compatible, with the following implications: First, you must upgrade your HALCON license (see [section 3.5](#) on page 36). Second, if you want to run applications created with an older release under the new version, you must regenerate the applications, as the new HALCON library is not binary compatible to the old one. The term 'applications' includes also image acquisition interfaces and extension packages you created yourself based on an older release. Note that a new version may also be source-code incompatible in some parts, e.g., the signature of an operator or a class method may have been changed. These changes are indicated in the release notes of the HALCON version. In such a case, you must adapt the source code of your application before regenerating it.

In contrast, a *maintenance release* is in most cases fully downward compatible to its corresponding version. This compatibility includes the license. Please note, however, that some maintenance releases may not be fully binary or source-code compatible because of technical reasons. In such cases, the release notes will contain corresponding warnings and describe how to proceed.



## 1.3 Supported Platforms and System Requirements

You can use HALCON under Windows, Linux, and macOS. The summary of system requirements is listed in [table 1.1](#); more details follow below.

Operating System	Processor	Compiler / Environment
Windows	Intel Pentium 4 / AMD Athlon 64 or higher	Visual Studio 2005 or higher
Windows x64	Intel 64 or AMD64	Visual Studio 2005 or higher
Linux x86_64	Intel 64 or AMD64	gcc 4.8 or higher
Linux armv7a	ARMv7-A with NEON support	gcc 4.8 or higher
macOS	Intel 64	Xcode

Table 1.1: Platforms supported by HALCON.

### Additional Linux Requirements

Support for OpenGL (Mesa packages) must be available. Also, libfreetype and libfontconfig must be installed.

Furthermore, an XServer has to be installed. This is required even for command-line tools provided with HALCON.

### Platform-Specific HALCON Versions

For each of the operating systems listed in [table 1.1](#) on page 9, platform-specific versions of HALCON's executables and libraries are provided. [Table 1.2](#) on page 10 lists all platform-specific versions with detailed system requirements. The name of the currently used version is stored in the environment variable HALCONARCH. On Windows and Linux, HALCON uses AVX2-optimized code for many operators, when run on a machine that supports AVX2.

Note that HALCON should also run on newer versions of the operating systems than the ones listed; however, we cannot guarantee this.

HALCONARCH appears in several directory paths: Executable HALCON programs like `hdevelop`, and DLLs like `halcon.dll` (Windows only), reside in `%HALCONROOT%\bin\%HALCONARCH%`. On Windows systems, this path is therefore automatically included in the environment variable `PATH`; on a Linux system, you must include it in your login script.

The libraries that you need for linking programs, e.g., `halcon.lib` (Windows) or `libhalcon.so` (Linux) reside in the directory `%HALCONROOT%\lib\%HALCONARCH%`. On macOS, the corresponding libraries are organized as frameworks in `/Library/Frameworks`.

HALCONARCH	Operating System, Processor
x86sse2-win32	Windows 7/8/8.1/10 or Windows Server 2008 R2/2012, on x86 processor with SSE2 extension, e.g., Intel Pentium 4 / AMD Athlon 64 or higher
x64-win64	Windows 7/8/8.1/10 or Windows Server 2008 R2/2012 x64 Edition, on Intel 64 or AMD64
x64-linux	Linux x86_64, libc.so.6 (GLIBC_2.17 or higher), libstdc++.so.6 (GLIBCXX_3.4.15 or higher), on Intel 64 or AMD64
armv7a-linux	Linux armv7a, Kernel with hidraw support, hard-float ABI, glibc 2.17 or higher, libstdc++.so 6.0.18 or higher
x64-macosx	OS X 10.10 or higher on Intel 64

Table 1.2: Values of HALCONARCH and detailed system requirements.

Please note that when creating a 64-bit application, both the development computer and the computer on which the application will run must be 64-bit platforms. On the other hand, you can use a 32-bit HALCON version on a 64-bit platform using the WOW64 (Windows-On-Windows 64-bit) subsystem.

Further note that in order to create .NET applications under Linux, you need to install Mono.

### Platform-Independent Applications

Even when using a platform-specific version of HALCON, you can still create platform-independent applications, in two ways:

- **With HDevelop**, HALCON’s integrated development environment (IDE). HDevelop programs are stored in a platform-independent format, thus, you can run them on any supported platform.
- **With HALCON/.NET**, HALCON’s interface to .NET programming languages. Applications written in .NET languages are stored in a platform-independent intermediate language, which is then converted by the so-called common language runtime into platform-specific code.

You can combine both methods by using HDevEngine/.NET to run HDevelop programs from a HALCON/.NET application.

## 1.4 Licensing

To run HALCON on a computer, you need a license. The license itself is typically stored in a file named “license.dat” or similar.

Licenses are always issued for a certain HALCON version (i.e., major release, see [section 1.2](#) on page 8), e.g., for HALCON 13.0. However, a license is not exclusively bound to this version: It is *upward compatible within the version number*, i.e., licenses for HALCON 13.0 are also valid for HALCON 13.0.1.

If you want to use different HALCON versions at the same time, from version 7.1 on the name of the license file is not restricted to “`license.dat`” anymore. Now, it has to begin with “`license`” and end with “`.dat`”, but in between other information can be included. Thus, different licenses for different versions (e.g., `license-13.0.dat` for version 13.0) can be stored in the same directory.

The three possible licensing types mainly correspond to the different HALCON versions described in [section 1.1](#) on page 7. Detailed information about HALCON licenses can be found in [chapter 3](#) on page 31.

- **Evaluation license**

To evaluate the full power of HALCON, you can obtain an evaluation license from your local distributor free of charge. This type of license is not bound to any computer hardware, i.e., you can use HALCON on any computer you installed it on; however, it is only valid for a limited time, typically for a month. Note that you may not use this license to develop commercial applications.

- **Development license**

To develop HALCON applications, whether in HDevelop or via a programming language, you need a development license. In contrast to the evaluation license, this license is permanent. Furthermore, this license is bound to a certain hardware component (network card or dongle, see [section 3.1](#) on page 31).

If you want to use HALCON on multiple computers simultaneously, you need a license for each of them.

- **Runtime license**

If you finished developing your application based on HALCON and now want to install and run it on a customer’s computer, you only need a runtime license. Like development licenses, runtime licenses are permanent and bound to a certain hardware component (network card or dongle).

As already noted, you can obtain runtime licenses that cover only parts of the functionality (so-called *modules*). Please contact your local distributor for more information.



## Chapter 2

# Installing HALCON

In this chapter, we show how to

- obtain HALCON ([section 2.1](#) on page 13), and install it for the first time ([section 2.2](#) on page 14),
- install additional parts ([section 2.3](#) on page 21),
- manually install a runtime version of HALCON ([section 2.5](#) on page 21),
- update HALCON to a newer maintenance release ([section 2.6](#) on page 23), and
- upgrade HALCON to a newer version ([section 2.7](#) on page 23).

Furthermore, this chapter explains how to

- uninstall HALCON ([section 2.9](#) on page 24),
- manage multiple versions in parallel ([section 2.10](#) on page 27),
- switch between HALCON for 32-bit and 64-bit Windows or vice versa ([section 2.11](#) on page 28),
- install updates of image acquisition interfaces ([section 2.12](#) on page 28), and
- install extension packages ([section 2.13](#) on page 28).

## 2.1 How to Obtain HALCON

You can obtain HALCON by downloading it from <http://www.halcon.com/download>. Note that you must first register yourself before downloading software. The download page provides separate files for the different configurations (see [section 1.1](#)).

## 2.2 Installing HALCON for the First Time

In the following sections, we explain how to install HALCON for the first time

- on Windows systems: [section 2.2.1](#)
- on Linux systems: [section 2.2.2](#) on page 18
- on macOS systems: [section 2.2.3](#) on page 20



**Administrator privileges** are required to install HALCON under Windows and macOS, and also on Linux systems if a dongle driver is used.

### 2.2.1 Installing HALCON under Windows

- Assisted installation: [section 2.2.1.1](#)
- Silent runtime installation: [section 2.2.1.2](#) on page 17

#### 2.2.1.1 Assisted Installation (full or runtime version)

To install HALCON on Windows systems, simply double-click the downloaded installer.

The installer checks for previous installations of HALCON. Depending on the installed version (see [section 1.2](#) on page 8), the installer will offer an appropriate action:

- If a different major version is installed, you can choose which version will be active after the installation.
- If a different minor version is installed, the installer will update the existing installation.

#### Step 1: Internal checks, license agreement, maintenance releases

First, the setup program checks whether your system meets the requirements for running HALCON (see [section 1.3](#) on page 9). Besides, it checks whether you already installed HALCON on this computer. If not, a license agreement is displayed; its text is stored in the file `eula.txt`, which will be installed in the folder you select for the installation.

The installer also checks for available maintenance releases (full version only). You can skip this step, e.g., if the computer is not connected to the internet. Afterwards, the most appropriate architecture for the installation is suggested (x86 or x64), if applicable.

#### Step 2: Select installation type

Then, you are asked to select between the following installation types which correspond to the HALCON configurations described in [section 1.1](#) on page 7. Note that you can install additional parts of HALCON at a later time by starting the setup program again and selecting the parts you need (see [section 2.3](#) on page 21). The runtime installer only supports the component selections “Runtime” and “Custom”.

**Full**

This installs the complete development version of HALCON, i.e., the full set of libraries and executables including interfaces to image acquisition devices and programming languages. Furthermore, it installs the full documentation, and the full set of example programs (see [section A.1](#) on page 43 for an overview), including all necessary images and 3D models.

**Compact**

This installs a minimal development version of HALCON, i.e., besides the full set of libraries and executables including interfaces to image acquisition devices and programming languages the installation encompasses only the User's Manuals and the Reference Manual. Note that neither examples nor images are installed.

**Runtime**

This installs the runtime version of HALCON, i.e., only the set of libraries including interfaces to image acquisition devices, I/O device interfaces, and programming languages that are necessary to run a HALCON application. Naturally, this type of installation encompasses neither documentation, examples nor images. However, it contains HDevEngine and the provided external procedures.

**Custom**

Like the Full and the Compact installation, this type installs the development version of HALCON. As its name suggests, it lets you select which parts of the documentation, examples, and images you want to be installed. Note that some HALCON experience is required to handle this type of installation.

**Step 3: Additional drivers for GigE Vision**

The installer offers to install the MVTec GigE Vision streaming filter driver. This option is recommended if you intend to acquire images from GigE Vision compliant cameras via the HALCON GigEVision interface because it increases the performance significantly.

**Step 4: Documentation language (full version only)**

By default, the documentation will be installed in English. The HALCON operator reference is also available in German and Japanese. You can select the desired language of this manual.

**Step 5: Select installation destination**

After these checks you can choose a folder where HALCON is to be installed, e.g., `C:\Program Files\MVTec\HALCON-13.0`.

**Step 6: Example programs and images (full version only)**

The installer will install example programs as shared user documents by default, i.e., in a location which is writable by all users. This is highly recommended because some of the example programs require write access to run properly. Alternatively, you can install these example programs inside the installation destination specified in the previous step. After the installation, the environment variable `%HALCONEXAMPLES%` points to the actual location of the example programs, and the environment variable `%HALCONIMAGES%` points to the location of the images.

### Step 7: The actual installation

Finally, the actual installation starts, which includes copying files to the destination folder (see [section A.1](#) on page 43 for an overview of HALCON's fileset), entering information in the Windows registry, and setting environment variables (see also [section A.2](#) on page 51). Depending on the installation type and content, it may be necessary to reboot the computer after the installation is finished.

### Step 8: HALCON Variable Inspect

HALCON includes an extension that simplifies the debugging of applications in Visual Studio. During the installation, the installer checks for a compatible version of Visual Studio (2013 or higher) and offers to install the extension. If you wish to install the extension later, double-click `%HALCONROOT%\misc\HALCON_Variable_Inspect.vsix` and follow the instructions. See the Programmer's Guide, [section 3.3](#) on page 30 for more information about HALCON Variable Inspect.

### Step 9: License installation (optional)

After the setup of HALCON has finished, the installer lets you install a license file. This step can be skipped if you have not yet obtained a license from your local distributor. To install the license at a later time, simply copy the obtained license file `license.dat` (or similar) to the directory `%HALCONROOT%\license`.

Apart from that, no further action on your part is required. You can immediately use HALCON, e.g., experiment with HDevelop if you have obtained a license already. A good starting point is the Windows start menu, via which you can read the manuals or the release notes, or start HDevelop.



If you are using a **CodeMeter dongle and CodeMeter Runtime** is running, CodeMeter Runtime needs to be at least version 5.00. Otherwise, the dongle is not recognized correctly, and HALCON throws an error regarding the license file.

### Step 10: Further configuration



Optionally, you can optimize **HALCON's automatic operator parallelization** to your computer as described in the Programmer's Guide, [section 2.1.1](#) on page 19.



### 2.2.1.2 Silent Installation (runtime version only)

This installation mode is provided for automatic, unattended installations of the runtime version of HALCON. Open a Windows command prompt (as Administrator), and change to the directory where you put the downloaded runtime installer.

Start the silent runtime installation using the /S switch:

```
halcon-13.0.1-runtime-windows.exe /S
```

In this mode, no warnings are given when encountering existing installations:

- Runtime binaries of existing HALCON 13 installations will be overwritten.
- Other versions will not be uninstalled.

The silent runtime installation supports the following additional command line parameters (only for first-time installations, not in the case of an update):

- /DEST="target directory"  
Default: %PROGRAMFILES%\MVTec\HALCON-13.0.
- /ARCH=[x86sse2-win32|x64-win64]  
Default: Best supported architecture is installed.
- /DRIVER=gigevision  
Default: No driver is installed.
- /UNSELECT=ocr  
Default: OCR fonts are installed.

All command line switches must be given in UPPER case as designated. Example:

```
halcon-13.0.1-runtime-windows.exe /S /DEST="C:\HALCON"
```

## 2.2.2 Installing HALCON under Linux

To install HALCON on Linux systems, extract the downloaded archive in an empty directory.

```
tar zxvf halcon-13.0.1-linux.tar.gz
```

To start the installation, execute the shell script `install-linux.sh`, which is located in the top-level directory of the extracted archive, e.g., by calling

```
sh install-linux.sh
```

### Step 1: Internal checks, architecture selection, license agreement

First, the setup program checks whether your system meets the requirements for running HALCON (see [section 1.3](#) on page 9). Then, a license agreement is displayed; its text is stored in the file `eula.txt`, which will be installed in the directory you select for the installation.

### Step 2: Select installation destination

The script will ask you in which directory you want to install HALCON; the environment variable `HALCONROOT` must be set to this directory later; see below. If the directory does not exist yet, the script offers to create it. On the other hand, if HALCON was already installed in the selected directory, the script asks whether to remove the old installation completely or replace existing files with the new ones.

### Step 3: Select installation type

Then, you are asked to select between different installation types, which correspond to those described in [section 2.2.1](#) on page 14. Note that you can install additional parts of HALCON at any time by extracting the archive again and copying the corresponding directories and files to the directory where you installed HALCON (see [section 2.3](#) on page 21). You can also execute the shell script `install-linux.sh` once again to install additional parts of HALCON.

### Step 4: The actual installation

Now, the actual installation starts, i.e., the requested parts are copied to the destination directory.

### Step 5: Documentation language

By default, the documentation will be installed in English. The HALCON operator reference is also available in German and Japanese. You can select the desired language of this manual.

### Step 6: Support for the ARMv7-A platform

If you intend to cross-compile HALCON applications for ARM<sup>®</sup>-based platforms, you should also install the required libraries for the `armv7a` architecture.

After the installation has finished, you should perform a runtime installation on the ARM platform: Copy the file `misc/linux/halcon-13.0.1-runtime-armv7a-linux.tar.gz` to an empty directory on the ARM platform, and follow the first steps of this section again (extract the archive and run the installation script). See [HALCON for ARM-based platforms](#) for platform-specific information.

## Step 7: Set environment variables

```
# Sample shell script for HALCON environment settings
# (sh syntax)
# If you are using the Bourne shell source this file with the following
# command:
# source .profile_halcon

HALCONARCH=x64-linux; export HALCONARCH
HALCONROOT=/opt/halcon; export HALCONROOT
HALCONEXAMPLES=${HALCONROOT}/examples; export HALCONEXAMPLES
HALCONIMAGES=${HALCONROOT}/examples/images; export HALCONIMAGES
PATH=${HALCONROOT}/bin/${HALCONARCH}:${PATH}
export PATH

if [ ${LD_LIBRARY_PATH} ] ; then
  LD_LIBRARY_PATH=${HALCONROOT}/lib/${HALCONARCH}:${LD_LIBRARY_PATH}
  export LD_LIBRARY_PATH
else
  LD_LIBRARY_PATH=${HALCONROOT}/lib/${HALCONARCH}; export LD_LIBRARY_PATH
fi
```

Figure 2.1: Example for a shell script with environment variables in `sh` syntax, generated when installing HALCON into the directory `/opt/halcon` on a Linux system.

After the installation, the following environment variables must be set or modified in order for HALCON to work (see [section A.2](#) on page 51 for more information about these and other environment variables):

- `HALCONROOT`: directory you installed HALCON in.
- `HALCONEXAMPLES`: directory the example programs are installed in (`HALCONROOT/examples`).
- `HALCONIMAGES`: directory the example images are installed in (`HALCONEXAMPLES/images`).
- `HALCONARCH`: select value corresponding to the used platform (see [table 1.2](#) on page 10).
- `PATH`: this system variable should include `HALCONROOT/bin/HALCONARCH`.
- `LD_LIBRARY_PATH`: this system variable should include `HALCONROOT/lib/HALCONARCH`.

It is recommended to set the environment variables in a login script or a shell resource script, e.g., `.cshrc` or `.profile`. **The installation script automatically creates two example shell scripts `.cshrc_halcon` and `.profile_halcon` in `HALCONROOT` which contain the necessary settings in `csh` and `sh` syntax, see [figure 2.1](#) on page 19.** The suitable shell script can be included in your login script. Note that different shells offer different commands to set environment variables, e.g., `setenv <variable> <value>` or `export <variable>=<value>`. Please consult your shell's documentation for further information. If a value consists of multiple items, those items must be separated by *colons*.

Make sure `LD_LIBRARY_PATH` is set correctly after a reboot, e.g., with:

```
echo $LD_LIBRARY_PATH
```



Some systems disallow setting `LD_LIBRARY_PATH` in `.profile`. If the variable is not set after reboot, you should try to set `LD_LIBRARY_PATH` in other initialization files like `.bashrc`. Consult the documentation that comes with your operating system.

### Step 8: Further configuration



Optionally, you can optimize **HALCON's automatic operator parallelization** to your computer as described in the Programmer's Guide, [section 2.1.1](#) on page 19.

In case that you have already obtained a license from your local distributor, you can now proceed with the installation of the license file `license.dat` which has to be placed in the directory `$HALCONROOT/license`.

If the license is bound to a USB dongle, you need to allow access to the `hidraw` device for CodeMeter dongles. This can be done by copying the file `$HALCONROOT/misc/linux/udev/rules.d/59-halcon-codemeter.rules` to the `/etc/udev/rules.d` system directory (see also [section 4.3.1](#) on page 40).

## 2.2.3 Installing HALCON under macOS

To install HALCON on macOS systems, simply double-click the downloaded installer.

### Step 1: License agreement

First, a license agreement is displayed that has to be accepted to continue the installation. This license can be printed or saved to disk for later reference. After the installation has finished, the file can be found in `/Library/Application Support/HALCON-13.0/eula.txt`.

### Step 2: Select installation destination

Select "Install for all users of this computer" and continue.

### Step 3: Select installation type

By default, HALCON will be installed completely, including the English documentation and the supplied example programs. The HALCON operator reference is also available in German and Japanese. To select another language, or skip other parts of the installation, click "Customize".

### Step 4: The actual installation

You will need root privileges to start the installation. The installer will then copy all required files to your computer (see [section A.1](#) on page 43 for an overview of HALCON's fileset).

### Step 5: License installation (optional)

After the setup of HALCON has finished, the installer lets you install a license file. This step can be skipped if you have not yet obtained a license from your local distributor. To install the license at a later time, simply copy the obtained license file `license.dat` (or similar) to the directory `/Library/Application Support/HALCON-13.0/license`.

### Step 6: Further configuration

You can optimize HALCON's **automatic operator parallelization** to your computer as described in the Programmer's Guide, [section 2.1.1](#) on page 19.



Apart from that, no further action on your part is required.

## 2.3 Installing Additional Parts of HALCON

### Windows systems

On Windows systems, you can install additional parts of HALCON at any time by starting the downloaded installer again.

### Linux systems

On Linux systems, you can install additional parts of HALCON at any time by starting the installer `install-linux.sh` from the downloaded archive another time.

### macOS systems

On macOS systems, you can install additional parts of HALCON at any time by starting the downloaded installer again.

## 2.4 Usage of the command `regsvr32` on Windows x64

Whenever the command `regsvr32` is used in this manual, you have to make sure to use the correct version of the binary on Windows x64.

If you are installing/uninstalling the 32-bit version of HALCON on Windows x64, use

```
C:\WINDOWS\SysWOW64\regsvr32
```

If you are installing/uninstalling the 64-bit version of HALCON on Windows x64, use

```
C:\WINDOWS\system32\regsvr32
```

## 2.5 Manually Installing a Runtime Version of HALCON on Windows

Usually, when a machine vision application is finished it has to be set up at a production site. This involves installing HALCON runtime versions on a number of computers. Depending on that number,

individual installations can become a nuisance. Quite often, a software distribution tool or script-based solution is used to install required programs on the client computers. This section shows the relevant steps of installing a HALCON runtime version manually. With this knowledge, the task of software distribution can be automated.



As an alternative, a **separate runtime installer is available for download**. This stripped-down installer features a silent installation mode (see [section 2.2.1.2](#) on page 17). See [section 2.1](#) on page 13 for download information.

You need administrator privileges to perform the manual installation.

1. Set the environment variables HALCONROOT and HALCONARCH. See also [section A.2](#) on page 51.
2. Copy the required runtime DLLs to, e.g., C:\%HALCONROOT%\bin\%HALCONARCH% (see [table 1.2](#) on page 10 for values of the environment variable HALCONARCH). The following DLLs are required: halcon.dll, the relevant HALCON language interface used by the application, e.g., halconcpp.dll, if used, the appropriate image acquisition device interface, e.g., hAcq1394IICD.dll, and, the required I/O device interface.

If you want to use HALCON/.NET, you must also copy the corresponding assemblies to the directory %HALCONROOT%\bin\dotnet20, or %HALCONROOT%\bin\dotnet35 (also see the Programmer's Guide, [section 16.1](#) on page 136).

If the application uses HALCON XL, the relevant DLLs or assemblies with the suffix x1 must be copied instead.

The HALCON DLLs must never be found in the %PATH% twice or even multiple times. Additionally, it is highly recommended not to copy the HALCON DLLs into the Windows system directories (C:\%WINDIR%, C:\%WINDIR%\system, and C:\%WINDIR%\system32).

3. Add the directory with the HALCON DLLs to the %PATH% environment variable, e.g., C:\%HALCONROOT%\bin\%HALCONARCH%. This step is not required if the application resides in the same directory as the DLLs.
4. Register halconx.dll (or halconxx1.dll) if the application uses the HALCON/COM interface. To do this, execute regsvr32 halconx.dll in the directory where the file resides (Windows x64 users: note [section 2.4](#) on page 21).
5. Register hdevenginex.dll (or hdevenginexx1.dll) if the application uses HDevEngine. To do this, execute regsvr32 hdevenginex.dll in the directory where the file resides (Windows x64 users: note [section 2.4](#) on page 21).
6. Copy the HALCON help files to %HALCONROOT%\help.
7. Copy the license file license.dat (or similar, see [section 1.4](#) on page 10) to %HALCONROOT%\license.
8. Depending on the application, one or more of the following directories need to be copied to %HALCONROOT% as well: calib, filter, lut, ocr, procedures.
9. If you intend to use the GenICamTL or USB3 Vision interface, copy the directory genicam to %HALCONROOT% as well.
10. If you intend to use the GigEVision interface, copy the directory genicam to %HALCONROOT% and install the MVTec GigE Vision Streaming Filter using the corresponding executable

(`GevStreamingFilter.exe` or similar) from the directory `misc`. Use the command line option `--help` for further instructions and return values.

## 2.6 Updating HALCON

With HALCON, the term “update” means to install a newer maintenance release over a release based on the same HALCON version, e.g., HALCON 13.0.1 over 13.0. As described in [section 1.2](#) on page 8, you can update HALCON without needing a new license.

When updating an existing HALCON installation under Windows the downloaded installer will ask you whether you want to replace the already installed components with the updated ones.

## 2.7 Upgrading HALCON

With HALCON, the term “upgrade” means to install a newer version over an older one, e.g., HALCON 13.0 over 12.0 or 12.0.1. As described in [section 1.2](#) on page 8, new versions are not compatible to older ones. Therefore, we recommend to **uninstall the older HALCON release before installing the new one**. On Windows systems, this is especially important in order to clean up the registry.

The easiest way to uninstall the older version on Windows is to start the installation of the new version, because the setup program offers to perform the uninstallation for you if it detects an older version. More information regarding uninstalling HALCON can be found in [section 2.9](#) on page 24. If you want to keep the older version, please refer to [section 2.10](#) on page 27.

The installation process itself is the same as the first-time installation described in [section 2.2](#) on page 14. Please note that after installing the new version you must upgrade the license as described in [section 3.5](#) on page 36.

## 2.8 HALCON Installer Switches under Windows

The installation process under Windows can be customized by calling the setup program with designated switches. This can be done from a Windows command prompt, or from a custom batch file. The following switches are recognized:

```
/CPU=[x86sse2 | x64]           Force architecture.  
/LANG=[english | german | japanese] Force language selection.
```

Also, a silent runtime installer exists which provides additional options for automated installations (see [section 2.2.1.2](#) on page 17). It can be downloaded from <http://www.halcon.com/download>.



## 2.9 Uninstalling HALCON

### 2.9.1 Uninstalling HALCON under Windows

The preferred method to uninstall HALCON is to use the automatic uninstallation program as described in the following section. In case you want to keep track of what is happening to your system, you may want to follow the instructions given in [section 2.9.1.2](#) on page 24.

#### 2.9.1.1 Uninstalling Automatically

There are multiple ways to uninstall HALCON; please note that not all are available for older versions of HALCON:

1. Select Start ▷ Programs ▷ MVTec HALCON 13.0 ▷ Uninstall HALCON in the Windows start menu.
2. Choose Add/Remove Programs in the system control panel.
3. When installing HALCON, the setup program checks whether there is an old version of HALCON and allows you to uninstall it. Note that during updating an existing HALCON installation under Windows the setup program will ask you whether you want to replace the already installed components with the updated ones.

Typically, this is all you have to do. If you encounter any problems, please refer to [section 4.2](#) on page 38.



Note that **the uninstallation removes exactly those files that were installed**. This has two implications: If you added files after the installation manually, e.g., new image acquisition interfaces, extension packages, images, or manuals, these files and the corresponding directories will “survive” the uninstallation. On the other hand, if you only modified a file, e.g., an example, without changing its name the uninstallation will remove it nevertheless. Therefore you might want to copy such files to another directory before starting the uninstallation.

The uninstallation process will not remove any *user-specific settings*. This means that entries concerning, e.g., the layout of HDevelop or its file history, will be left in the file `%APPDATA%\MVTec\HDevelop.ini`. If you have run the utility `hcheck_parallel`, AOP information has been stored in `%ProgramData%\MVTec\HALCON 13.0\.aop_info`. You may remove these files manually without risk. Moreover, the uninstaller does not remove the MVTec GigE Vision streaming filter driver if it is installed. This driver needs to be removed separately.

#### 2.9.1.2 Uninstalling Manually

The commands given in the following description should be entered in a Windows command prompt, which can be obtained by entering `cmd.exe` in the dialog Start ▷ Run. You need administrator privileges to perform the uninstallation.

1. Unregister the HALCON/COM interface and the COM version of HDevEngine (Windows x64 users: note [section 2.4](#) on page 21). If you have been using HALCON XL, append the suffix `x1`



to the .dll files in the following commands (thus, halconx.dll becomes halconxx1.dll, for example).

```
regsvr32 /u "%HALCONROOT%\bin\%HALCONARCH%\halconx.dll"
regsvr32 /u "%HALCONROOT%\bin\%HALCONARCH%\hdevenginex.dll"
```

- For extensive cleaning of the Windows registry you can optionally run the program %HALCONROOT%\misc\x86-win32\clean\_reg\_halcon.exe.
- Delete the installation directory. You can also use Windows Explorer to do this. Please note that **the license file and any local additions to this directory will be lost**. A backup of these files is highly recommended.

```
rmdir /S "%HALCONROOT%"
```

- Delete all HALCON registry keys. Replace x.x at the end of the following command with the version number you are uninstalling. Alternatively, start regedit.exe to use the Windows registry editor to delete the keys.

```
reg delete HKLM\SOFTWARE\MVTEC\HALCON\x.x} (Windows)
reg delete HKLM\SOFTWARE\Wow6432Node\MVTEC\HALCON\x.x} (Windows x64)
```

You can query all installed versions of HALCON using this command:

```
reg query HKLM\SOFTWARE\MVTEC\HALCON (Windows)
reg query HKLM\SOFTWARE\Wow6432Node\MVTEC\HALCON (Windows x64)
```

- Delete all environment variables set by HALCON. The indented lines must be appended to the preceding lines separated by a space character. See [section A.2](#) on page 51 on how to edit environment variables using the Windows GUI. Please also use the GUI to manually remove the HALCON binary directory from the environment variable PATH.

```
reg delete "HKLM\SYSTEM\CurrentControlSet\Control\Session Manager\Environment"
/V HALCONROOT
reg delete "HKLM\SYSTEM\CurrentControlSet\Control\Session Manager\Environment"
/V HALCONARCH
reg delete "HKLM\SYSTEM\CurrentControlSet\Control\Session Manager\Environment"
/V HALCONEXAMPLES
reg delete "HKLM\SYSTEM\CurrentControlSet\Control\Session Manager\Environment"
/V HALCONIMAGES
```

- Delete the uninstall information created when HALCON was installed. Replace <ID> with the actual HALCON GUID, which depends on the installed version:  
 HALCON 6.1 → BBEC9F40-4A36-11D6-A14C-00E0296C2846  
 HALCON 7.0 → 47F424B4-1077-11D8-A0D3-00E01883F42C  
 HALCON 7.1 → 0B2DE0B7-FD31-11D9-A19F-00E01883F42C  
 HALCON 8.0 → 096CE3F7-2FD9-4460-A270-F9F4740DB91B

```
rmdir /S "%ProgramFiles%\InstallShield Installation Information\{<ID>}"
reg delete HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall\{<ID>}
```

For HALCON 9.0 or higher, please use the following key:

```
reg delete "HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall\
MVTec HALCON xxx" (Windows)
reg delete "HKLM\SOFTWARE\Wow6432Node\Microsoft\Windows\CurrentVersion\
Uninstall\MVTec HALCON xxx" (Windows x64)
```

where xxx has to be replaced with the actual version number, e.g., 12.0.

## 2.9.2 Uninstalling HALCON under Linux

HALCON provides no uninstallation script for Linux systems, therefore you must perform the uninstallation manually.



Please note: The following procedure will **delete your local additions to the HALCON base directory**. To check for any local additions and changes beforehand, extract the downloaded archive, e.g., into /tmp/halcon and run

```
diff -q -r /tmp/halcon $HALCONROOT | grep $HALCONROOT
```

The actual uninstallation consists of simply removing the content of the HALCON base directory \$HALCONROOT and all its subdirectories, e.g., by executing

```
rm -rf $HALCONROOT
```

Furthermore, remove the subdirectory `.hdevelop` of the directory referenced by the environment variable `HOME` (see [section A.2](#) on page 51); `HDevelop` creates this directory to save options, window positions, and the file history. If you have run the utility `hcheck_parallel`, AOP information has been stored in `$HALCONROOT/.aop_info`. This file can also safely be deleted.

Finally, delete references to HALCON from the environment variables (see [section 2.2.2](#) on page 18).

## 2.9.3 Uninstalling HALCON under macOS

To uninstall HALCON from macOS systems, run the provided shell script. The 'x.x' in the middle of the following path should represent the version number you want to uninstall (e.g. 12.0). The same applies to 'halconx', where the x should be replaced by the version number (e.g. halcon12).

```
/Library/Application\ Support/HALCON-x.x/bin/remove_halconx_installation.sh
```

For example, if you want to uninstall HALCON 12, you have to run the following shell script:

```
/Library/Application\ Support/HALCON-12.0/bin/remove_halcon12_installation.sh
```

Note that the script for uninstalling HALCON 11.0 is for the first time provided with HALCON 12.0.

This script will simply remove the content of the various HALCON directories and their subdirectories and discard the corresponding package receipt data.

The script will not remove the preference file that HDevelop creates to save options, window positions and the file history. To remove this file, run the following command in Terminal.app:

```
rm $HOME/Library/Preferences/com.mvtec.HDevelop.plist
```

## 2.10 Managing Multiple HALCON Versions

### Linux systems

On Linux systems, you can switch between different HALCON versions by setting the environment variable `HALCONROOT` accordingly. Note that in order for this method to work, paths based on `HALCONROOT` in other environment variables like `PATH` and `LD_LIBRARY_PATH` must use the variable and not its content. See [figure 2.1](#) on page 19 for an example.

### Windows systems

Under Windows, you must adapt those environment variables that are set during the installation, i.e., `HALCONROOT`, `HALCONARCH`, `PATH`, `HALCONEXAMPLES`, and `HALCONIMAGES`, and those you set yourself (e.g., `HALCONEXTENSIONS`). Please refer to [section A.2](#) on page 51 for more information about setting environment variables.

If you are using the HALCON/COM interface or the COM version of HDevEngine, you must also re-register the corresponding DLLs `halconx.dll` or `hdevenginex.dll`, for example as follows: Open a Windows Command Prompt and change into the subdirectory `bin\%HALCONARCH%` of the root directory of your “old” HALCON installation (please note that versions older than HALCON 8.0 did not set the environment variable `HALCONARCH` and used different names for the platform-specific subdirectories!). Unregister `halconx.dll` or `hdevenginex.dll` (Windows x64 users: note [section 2.4](#) on page 21):

```
regsvr32 /u halconx.dll  
regsvr32 /u hdevenginex.dll
```

Then change into the corresponding subdirectory of your other HALCON installation and register its `halconx.dll` or `hdevenginex.dll` by typing

```
regsvr32 halconx.dll  
regsvr32 hdevenginex.dll
```

With the same method, re-register `hdevenginex.dll`, i.e., the DLL of the COM version of HDevEngine.

If you are using HALCON/COM XL, you must re-register `halconxxl.dll` and `hdevenginexxl.dll` instead.

As an alternative to the Command Prompt, you can unregister and register `halconx.dll` or `hdevenginex.dll` via the dialog `Start > Run` together with the Windows Explorer: In the latter, “open” the directory `bin\%HALCONARCH%` of the root directory of your old HALCON installation. Now, type `regsvr32 /u` in the dialog `Run` and then drag and drop `halconx.dll` or `hdevenginex.dll` from the Windows Explorer into the dialog, where it automatically appears with the full path. To execute the command, click `OK`. Then, open the directory `bin\%HALCONARCH%` of the root directory of the other HALCON installation in the Windows Explorer, type `regsvr32` in the dialog `Run`, drag and drop `halconx.dll` or `hdevenginex.dll` from the Windows Explorer into the dialog, and again click `OK`.

## 2.11 Switching between Different HALCON Platform Versions under Windows

As described in [section 1.3](#) on page 9, HALCON is provided for different platforms. However, only the first installation sets the environment variable `PATH` (see [section A.2](#) on page 51). If you want to switch e.g., from Windows 32-bit to Windows 64-bit, you must adapt the environment variable `HALCONARCH` accordingly (see [table 1.2](#) on page 10), which is referenced in `PATH`.

## 2.12 Installing HALCON Image Acquisition Interfaces

With every HALCON installation, you automatically obtain the latest release of the currently available image acquisition interfaces (see also [section A.1](#) on page 43). In between HALCON releases, however, image acquisition interfaces might be updated by MVTec or the manufacturer of an image acquisition device. Such updates are indicated on MVTec’s WWW server, to which you can connect by selecting HDevelop’s menu entry `Help > HALCON News (WWW)` or in the Start Dialog which appears when starting HDevelop. You can then download the interface together with its documentation and HDevelop example programs.

## 2.13 Installing HALCON Extension Packages

The HALCON Extension Package Interface enables you to integrate newly developed image processing algorithms into HALCON in the form of so-called *extension packages*. The same mechanism is used by MVTec to extend the current HALCON release with additional functionality. Which extensions packages are currently available can be checked by selecting HDevelop’s menu entry `Help > HALCON News (WWW)`, which connects to MVTec’s WWW server.

This section describes how to integrate a (downloaded) package named `newextpkg` in order to use it within your HALCON system.

First, unpack the package to a directory of your choice, e.g., `%HALCONROOT%`. Then, add the *complete* path of the package, e.g.,

```
%HALCONROOT%\packages\newextpkg
```

to the environment variable HALCONEXTENSIONS. Note, that the delimiter between paths in an environment variable is a semicolon on Windows systems and a colon on Linux/macOS systems.

**Never change the name of an extension package or the corresponding names of the libraries or DLLs contained in it.** These names are encoded *within* the libraries/DLLs. If you change the names this information will no longer match. Thus, the loader of the operating system will fail to open the dynamic libraries.



If the package contains images used, e.g., within example programs we recommend to include the (complete) path to the corresponding directory `images` within the package in the environment variable HALCONIMAGES (see [section A.2](#) on page 51) to access those images without specifying a complete path.

### 2.13.1 Using an Extension Package Within HDevelop

In order to use a new package within HDevelop under Windows/macOS, you just need to restart the program. HDevelop automatically integrates all extension packages specified in HALCONEXTENSIONS, i.e., the operators contained in a package can be accessed and used like any other HALCON operator.

Under Linux, you must include the package library subdirectory (i.e., `lib/$HALCONARCH`) in the environment variable LD\_LIBRARY\_PATH before starting HDevelop the first time (see [table 1.2](#) on page 10 for the possible values of HALCONARCH).

### 2.13.2 Using an Extension Package in a Stand-Alone Application

If you want to generate a stand-alone application that uses an extension package, you have to link the package libraries (DLLs under Windows, shared libraries under Linux/macOS) to the application code, in addition to the HALCON library.

#### 2.13.2.1 Using an Extension Package Under Windows

In order to create new application programs you have to link the corresponding language interface library, e.g., `packagecpp.lib` for a C++ application, to your objects. Furthermore, you will need the HALCON interface library, in the example of a C++ application `halconcpp.lib`, as for any HALCON application.

To be able to link the package DLL to your application program, the *complete* DLL file path of the new package, e.g.,

```
%HALCONROOT%\packages\newextpkg\bin\%HALCONARCH%
```

must be added to the environment variable PATH (see [table 1.2](#) on page 10 for the possible values of HALCONARCH).

**Do not copy a package DLL into the Windows system directories**, as it would be loaded twice in this case!



### 2.13.2.2 Using an Extension Package Under Linux

In order to create new application programs, you must link `libnewextpkg.so` and the corresponding language interface library, e.g., `libnewextpkgcpp.so` for a C++ application, to your objects (besides `libhalcon.so` and the HALCON interface library, in the example of a C++ application `libhalconcpp.so`, as for any HALCON application).

Furthermore, you have to add the path to the package library subdirectory `lib/$HALCONARCH` to the environment variable `LD_LIBRARY_PATH`, otherwise the loader will fail to access the libraries.

### 2.13.2.3 Using an Extension Package Under macOS

In order to create new application programs, you must link `libnewextpkg.dylib` and the corresponding language interface library, e.g., `libnewextpkgcpp.dylib` for a C++ application, to your objects (besides `libhalcon.dylib` and the HALCON interface library, in the example of a C++ application `libhalconcpp.dylib`, as for any HALCON application).

## Chapter 3

# All About HALCON Licenses

Section 1.4 on page 10 already contained an overview of the possible licensing schemes. In this chapter, you will find detailed information about how to obtain and install

- evaluation licenses (section 3.2 on page 33),
- development licenses (section 3.3 on page 33), and
- runtime licenses (section 3.4 on page 34),

Finally, section 3.5 on page 36 shows how to upgrade a license.

### 3.1 What is a License?

HALCON licenses are stored in so-called *license files*. The content of these files specifies

- what is licensed (e.g., development version, runtime version, etc.)
- whether the license is temporary (e.g., evaluation license) or permanent
- the hardware to which the license is bound (see below)

License files are named `license.dat` (or `license-13.0.dat` or similar, see section 1.4 on page 10) and reside in the subdirectory `license` of the folder where you installed HALCON. **Note that HALCON will not run if you modify the license keys within the license file manually!**



Licenses allow to run exactly one installation of HALCON at a time. The license validation is done on the local computer. To have additional people use HALCON on different computers at the same time, additional licenses have to be purchased. However, licenses can travel between computers by moving the hardware they are bound to (see below).

## Network Card Versus Dongle Binding

As noted in [section 1.4](#) on page 10, development and runtime licenses are bound to a certain hardware component. This is either the *network card* (see [section 3.3.1](#) on page 34) or a *dongle* (see [section 3.3.2](#) on page 34).

Dongle-bound licenses allow to use HALCON on different computers by moving the dongle. Of course, network cards can also be switched between computers, but in practice they can be regarded as fixed. Thus, if you want to develop applications with HALCON on more than one stand-alone computer at different times, the easiest solution is to obtain a dongle-bound license.

## Identifying the Hardware

The license manager software identifies a network card or a HALCON dongle by a so-called *host ID*. A valid host ID is the unique, immutable, machine-readable identification of an actual piece of hardware as devised by the hardware vendor.

HALCON includes a tool to query the host IDs from the command line. Open a Windows Command Prompt or a Linux/macOS shell, and enter the following command:

```
hhostid
```

This command produces a list of host IDs, which are available for licensing. For example:

```
0d00cafebabe 3-3123456
```

Use `hhostid -i` to get additional information, such as the type of a certain host ID:

```
hhostid -i
#0: 0d00cafebabe [MAC] <Local Area Connection>
#1: 3-3123456 [CM] <CM Container>
```

Each output line lists the following properties: First, the running number followed by the actual host ID is displayed. In the case of network adapters, the *permanent* MAC address is displayed. The host ID type is displayed in square brackets (MAC for network adapters, CM for HALCON dongles). The value in angle brackets shows the interface name as reported by the operating system. If the currently assigned MAC address of a network adapter differs from its permanent address, it would be reported here as well. HALCON only supports MAC based licenses bound to universally administered, permanent MAC addresses. Locally administered MAC addresses are rejected.

See [section 4.3.1](#) on page 40 for a detailed description on solving problems extracting the host ID.

HDevelop automatically checks whether any network cards or HALCON dongles are present and displays their host IDs in the menu item:

```
Help > About.
```

For example, the following information will be displayed on a computer equipped with a network card and a dongle:



```
HDevelop version: 13.0 (01.11.2016)
HALCON version: 13.0 (01.11.2016)

Platform version: x64-win64 (avx2)

(c) 1996-2016
MVTec Software GmbH, Munich, Germany

Number of processors: 4

The host IDs of this computer are:
0d00cafebabe          (network card ID)
3-3123456             (dongle ID)
```

## 3.2 Evaluation Licenses

As already noted in [section 1.4](#) on page 10, with an evaluation license you can evaluate the full functionality of HALCON free of charge on any computer. The only restrictions are that evaluation licenses are valid only for a limited time (typically a month), and no commercial applications may be developed.

### Step 1: Obtain the license

You can obtain an evaluation license from your local distributor.

### Step 2: Install the license

“Installing” the license simply means placing the license file into the subdirectory `license` of the folder where you installed HALCON. If necessary, rename the file to `license.dat` (or `license-13.0.dat` or similar, see [section 1.4](#) on page 10).

Note that you can evaluate HALCON on any computer where you installed HALCON just by copying the evaluation license file into the corresponding subdirectory `license`. You can also evaluate HALCON under different operating systems.

## 3.3 Development Licenses

Like the evaluation license, a development license allows you to use the full functionality of HALCON including the development tools like HDevelop (see also [section 1.4](#) on page 10). However, it must be bound to a certain hardware component (see also [section 3.1](#) on page 31). The following sections describe how to proceed to obtain and install a

- license bound to a network card ([section 3.3.1](#))
- license bound to a dongle ([section 3.3.2](#) on page 34)

### 3.3.1 License Bound to a Network Card

#### Step 1: Extract the host ID

The easiest way to extract the host ID is to execute the following command from a Windows Command Prompt or a Linux/macOS shell.

```
hhostid -i
```

All host IDs of type MAC can be used for licensing. See [section 3.1](#) on page 32 for more information.

#### Step 2: Obtain the license

Send the host ID of the network card to your local distributor. The distributor then sends you a *license file*.

#### Step 3: Install the license

Place the license file into the subdirectory `license` of the folder where you installed HALCON. If necessary, rename the file to `license.dat` (or `license-13.0.dat` or similar, see [section 1.4](#) on page 10).

### 3.3.2 License Bound to a Dongle

#### Step 1: Obtain dongle and license



Please note that **you cannot use any dongle but only those supplied by MVTec via your local distributor**. Currently, HALCON supports USB dongles.

The distributor will send you the dongle together with a corresponding *license file*. The dongle ID is printed on the dongle.

#### Step 2: Install the license

Place the license file into the subdirectory `license` of the folder where you installed HALCON. If necessary, rename the file to `license.dat` (or `license-13.0.dat` or similar, see [section 1.4](#) on page 10).

If you want to use HALCON on more than one computer by switching the dongle between them, repeat this step for every computer.

## 3.4 Runtime Licenses

In contrast to a development license, a runtime license only allows to run HALCON applications. Furthermore, a runtime license can be restricted to a set of selected modules if your application does not require the full functionality of HALCON. The list of required modules of an application is determined in the following way:

## Step 1: Extract the required modules

To extract the modules that are used by an application proceed as follows:

1. If the application is running in HDevelop, select the menu item `File > Properties`, which will open a dialog. In its tab `Used Modules` the used modules are listed (see the HDevelop User's Guide, [section 6.2.1.15](#) on page 69, for more information). [Figure 3.1](#) shows the result for an OCR application.

If you click `Copy to Clipboard`, the required modules are saved in the clipboard, from where you can insert them in other applications.

Please note that this method determines the list of used modules by inspecting *all* operators of the current program, no matter if they can be reached or not. If the program contains operator calls that are never executed, it is recommended to deactivate the corresponding program lines using `F4` before opening this dialog to get a correct list of used modules.




Figure 3.1: Used modules for an OCR application.

2. If the application is written in a programming language (C, C++, C#, VB.NET, etc.), insert the operator `get_modules` (see the corresponding entry in the HALCON Reference Manuals for more information) at the end of the program. Note that **the operator `get_modules` will only return the correct modules if all HALCON operators used in the application are executed at least once.**



## Step 2: Extract the host ID

Please refer to [section 3.3.1](#) on page 34 (network card) for information about how to extract the host ID. If you choose a dongle-bound license, no further action is required as you get the dongle together with the license (see [section 3.3.2](#) on page 34).

## Step 3: Obtain the license

Send the determined module names and – except in case of a dongle-bound license – the extracted host ID to your local distributor.

The distributor then sends you a license file. If you requested a dongle-bound license, you will also receive the dongle.

#### **Step 4: Install the license**

Place the license file into the subdirectory `license` of the folder where you installed HALCON. If necessary, rename the file to `license.dat` (or `license-13.0.dat` or similar, see [section 1.4](#) on page 10).

### **3.5 How to Upgrade a License**

If you upgrade a HALCON license to a newer version, e.g., from HALCON 12.0.x to HALCON 13.0, your distributor provides you with a new license file which contains new license keys. This new license file should replace the old one in `%HALCONROOT%\license\license.dat`.

# Chapter 4

## Troubleshooting

This chapter offers help for problems encountered during installing or uninstalling HALCON on Windows systems (section 4.1 on page 37 and section 4.2 on page 38, respectively), with the licensing mechanism (section 4.3 on page 39), or when starting HDevelop or your own HALCON applications (section 4.4 on page 40) and other miscellaneous problems.

Note that throughout the chapter the environment variable HALCONARCH is referenced. See table 1.2 on page 10 for the possible values of this variable.

### 4.1 Problems During Installation (Windows)

- **Registration of halconx.dll or hdevenginex.dll failed**

On some systems you might get a warning message that the HALCON/COM interface library halconx.dll or hdevenginex.dll failed to self-register. A possible cause for this may be that the Microsoft library at1.dll was not registered properly. This library resides in the directory %SystemRoot%\system32, e.g., C:\WINNT\system32. To register the library, open a Windows Command Prompt, change into the directory %HALCONROOT%\misc\x86-win32, and execute the supplied program reg\_halconx twice as follows:

```
reg_halconx at1.dll
reg_halconx
```

The first call of reg\_halconx registers at1.dll, the second one registers halconx.dll.

As an alternative to the Command Prompt, you can use the dialog Start ▸ Run; here, you can select the program via the button Browse or drag and drop reg\_halconx from the Windows Explorer, followed by the library name if necessary. Note that by default the Windows Explorer does not show DLL files, unless you explicitly tell it to do so.

- **Installer fails to detect SSE2**

In rare cases the installer fails to detect the SSE2 capabilities of the processor. You can force the installation of the SSE2 version by calling the installer with the command line option /CPU=x86sse2. For example:

```
E:\install-windows\setup.exe /CPU=x86sse2
```

See [section 2.8](#) on page 23 for information about installer switches.

## 4.2 Problems During Uninstallation (Windows)

- **Unregistration of halconx.dll**

If you had to register the HALCON/COM interface library `halconx.dll` manually as described in [section 4.1](#) on page 37, you must unregister it manually before you can uninstall HALCON. To do so, open a Windows Command Prompt, change into the directory `%HALCONROOT%\misc\x86-win32`, and execute the supplied program `reg_halconx` as follows:

```
reg_halconx /u
```

As an alternative to the Command Prompt, open the dialog `Start > Run`, select the program `reg_halconx` via the button `Browse`, append the option `/u`, and then click `OK`.

- **Uninstallation failed**

If the automatic uninstallation fails for another reason, proceed as follows:

- Start `regedit` and delete the following key:

On 32-bit Windows:

```
HKEY_LOCAL_MACHINE -> SOFTWARE -> MVTec -> HALCON -> x.x
```

On 64-bit Windows:

```
HKEY_LOCAL_MACHINE -> SOFTWARE -> Wow6432Node -> MVTec -> HALCON -> x.x
```

- **For recent versions (HALCON 9.0 or higher)**

Also delete the following key:

On 32-bit Windows:

```
HKEY_LOCAL_MACHINE -> SOFTWARE -> Microsoft -> Windows ->
CurrentVersion -> Uninstall -> MVTec HALCON x.x
```

On 64-bit Windows:

```
HKEY_LOCAL_MACHINE -> SOFTWARE -> Wow6432Node -> Microsoft -> Windows ->
CurrentVersion -> Uninstall -> MVTec HALCON x.x
```

- **Only for HALCON 8.0**

Also delete the key

```
HKEY_LOCAL_MACHINE -> SOFTWARE -> Microsoft -> Windows ->
CurrentVersion -> Uninstall ->
{096CE3F7-2FD9-4460-A270-F9F4740DB91B}
```

- **Only for HALCON 7.1**

Also delete the key

```
HKEY_LOCAL_MACHINE -> SOFTWARE -> Microsoft -> Windows ->
  CurrentVersion -> Uninstall ->
  {0B2DE0B7-FD31-11D9-A19F-00E01883F42C}
```

- **Only for HALCON 7.0**

Also delete the key

```
HKEY_LOCAL_MACHINE -> SOFTWARE -> Microsoft -> Windows ->
  CurrentVersion -> Uninstall ->
  {47F424B4-1077-11D8-A0D3-00E01883F42C}
```

- **Only for HALCON 6.1**

Also delete the key

```
HKEY_LOCAL_MACHINE -> SOFTWARE -> Microsoft -> Windows ->
  CurrentVersion -> Uninstall ->
  {BBEC9F40-4A36-11D6-A14C-00E0296C2846}
```

- **Only for HALCON releases < 6.1**

Also delete the key

```
HKEY_LOCAL_MACHINE -> SOFTWARE -> Microsoft -> Windows ->
  CurrentVersion -> Uninstall -> HALCON
```

- Using, e.g., the Windows Explorer, delete the directory

```
%ALLUSERSPROFILE%\Start Menu\Programs\MVtec HALCON x.x
```

- Delete the environment variables HALCONROOT and HALCONIMAGES in Start > Settings > Control Panel > System (Windows Vista and Windows 7: ... > System > Advanced System Settings).
- Finally, delete the contents of the HALCON directory and all its subdirectories.

## 4.3 Problems Concerning Licenses

If you encounter problems with your HALCON license even though your license file exists and is located in the correct directory, a first step is always to check if the host ID identifying your network card or dongle matches the entry in the license file (see the corresponding sections in [chapter 3](#) on page 31). If the two do not match, please send the new identifying information to your distributor. See [section 4.3.1](#) if you encounter problems with extracting the identifying information.

### 4.3.1 Extracting Host IDs

- **hhostid does not return a dongle ID**

Please note that only HALCON dongles (orange) are reported by hhostid. Other dongles (e.g., blue MERLIC dongles) are not supported.

- **hhostid does not return a MAC address**

This might happen if you call hhostid from a virtualized environment using locally administered MAC addresses. HALCON only supports MAC based licenses bound to universally administered, permanent MAC addresses. Locally administered MAC addresses are rejected.

- **hhostid shows no dongle ID on Linux even though a HALCON dongle is plugged in**

On Linux, the hidraw device must exist. This device is usually available on systems using the default kernel configuration. However, on embedded systems, this device might not be configured, in which case hhostid would not be able to access the dongle ID. The solution is to enable the hidraw device in the kernel configuration (CONFIG\_HIDRAW=y) and to build a custom kernel.

In addition, HALCON needs read/write permissions on the hidraw device. The following udev rule is required to achieve this:

```
# Udev rules to allow access to hidraw device for CodeMeter dongles

ACTION=="remove", GOTO="halcon-cm_end"

SUBSYSTEM=="hidraw", ATTRS{idVendor}=="064f", ATTRS{idProduct}=="2af9", MODE="666"

LABEL="halcon-cm_end"
```

You can add this rule to /etc/udev/rules.d yourself, or copy the file \$HALCON-ROOT/misc/linux/udev/rules.d/59-halcon-codemeter.rules to that directory.

## 4.4 Troubleshooting in HDevelop or HALCON Applications

### 4.4.1 Startup Errors

This section explains miscellaneous error messages when starting HDevelop or your own HALCON applications and their reasons.

- **Error using license file**

This error message might have several reasons:

- The file %HALCONROOT%\license\license.dat is missing and/or not readable.
- Your license is not valid on this machine.
- If there is more than one user trying to use HALCON via remote access, the second user gets an error message.



- **No license for this operator**

The operator which you try to execute belongs to a HALCON module that is not licensed (see [section 3.4](#) on page 34). Obtain a new license including this module.

- **hdevelop: Command not found (Linux)**

Check your system environment variable PATH. It must include the path \$HALCON-ROOT/bin/\$HALCONARCH.

- **lib\* : can't open file (Linux)**

Check the system variable LD\_LIBRARY\_PATH (see [section A.2](#) on page 51).

- **No help files for package <package-name> in directory <directory>**

Possible reasons for this error message are:

- No files %HALCONROOT%\help\\* (if the package name is “system”) or no help files in one of the user packages.
- If the package name is “system”: Wrong HALCONROOT.
- Check the file permissions. Probably HDevelop cannot access important files.

- **Help file for package <package-name> is corrupt**

Possible reasons for this error message are:

- If the package name is “system”: Inconsistent version of %HALCONROOT%\help\\* or wrong HALCONROOT.
- If the package name is that of a user package: Inconsistent version of the help files of this package.

- **Can't open display (Linux)**

If you see an error message like this you may have a wrong system variable DISPLAY and/or your program is not allowed to open a window by the specified X-server.

- **No refresh of window content on a Linux system**

On some Linux systems the default behavior regarding occluded windows may be set in an inconvenient way for HALCON. The result is that if a window is temporarily occluded by another window, its content is not saved and restored anymore, i.e., windows remain “black” after uncovering. An example for this are all SuSE Linux distributions  $\geq 7.0$ . The corresponding property is called “backing-store”; you can check the current setting of this property by typing (the following example corresponds to a SuSE 8.2 Linux system):

```
xdpyinfo | grep backing-store
```

which should result in the output like

```
options:    backing-store YES, save-unders YES
```

if the window content is saved and restored. You can change this behavior by changing the configuration file of your X server. It usually resides in /etc/X11/xorg.conf if you are using Xorg, or

in `/etc/X11/XF86Config` if you are using XFree86. Consult your system's documentation if in doubt.

You will probably need to become root to modify this file. Open the file in a text editor, find the section named "Device", and add the following option to this section:

```
Section "Device"
...
Option      "BackingStore" "True"
EndSection
```

Alternatively, you can modify the file `Xservers` residing in the directory `/usr/lib/X11/xdm` (or `/opt/kde3/share/config/kdm` in case of newer Linux versions), see your system's documentation. Note, that you probably need root privileges to modify this file. Append the option `+bs` (i.e., "plus backing-store") to the line that starts the local X server:

```
:0 local /usr/X11R6/bin/X :0 vt07 +bs
```

Now, stop and start the X server again (by using the appropriate commands or by rebooting your computer); the command `xdpyinfo` now should yield the output shown above.

# Appendix A

## More on the Installation

This appendix contains information about

- the installed file structure ([section A.1](#)),
- the relevant environment variables ([section A.2](#) on page 51),
- the registry keys on Windows systems ([section A.3](#) on page 53), and

### A.1 The Installed File Structure

#### A.1.1 Main Directory

Let's take a look at the installed file structure in the directory designated by the environment variable HALCONROOT. The default location suggested by the installer is operating system-dependent:

Windows	C:\Program Files\MVTec\HALCON-13.0
Linux	/opt/halcon
macOS	/Library/Frameworks/HALCON.framework (most of the following files are installed here unless stated otherwise)

In the following, the most important directories and files are described briefly. Please note that, depending on your installation, not all directories may be present.

### A.1.1.1 Windows

The default location for Windows is C:\Program Files\MVTec\HALCON-13.0:

<code>bin</code>	Contains HALCON programs, for example HDevelop, in subdirectories corresponding to the different platforms. This directory also contains the DLLs of the HALCON libraries, the DLLs for the supported image acquisition interfaces, and I/O device interfaces. The subdirectories <code>dotnet20</code> and <code>dotnet35</code> contain the HALCON/.NET assemblies based on .NET Framework 2.0, and .NET Framework 3.5, respectively.
<code>calib</code>	Contains description files for the calibration plates, which you can use to calibrate your camera.
<code>doc\html\manuals</code>	Contains some of the User's Manuals.
<code>doc\html\reference\acquisition</code>	Contains the HTML documentation of the HALCON Image Acquisition Interfaces.
<code>doc\html\reference\io</code>	Contains the HTML documentation of the I/O device interfaces.
<code>doc\html\reference\operators</code>	Contains the HALCON Operator Reference.
<code>doc\index</code>	Contains the index files that are relevant for the full-text search of the documentation.
<code>doc\macros</code>	Contains the style files for the HALCON Operator Reference in all translated languages. These files set the layout and provide macros for names and formatting.
<code>doc\pdf\manuals</code>	Contains the PDF version of the User's Manuals.
<code>doc\pdf\reference</code>	Contains the PDF version of the HALCON Operator Reference in HDevelop syntax.
<code>doc\pdf\solution_guide</code>	Contains the PDF version of the <a href="#">Solution Guide I</a> , the Solution Guide II, and Solution Guide III.
<code>filter</code>	Contains predefined filter masks.

<code>genicam</code>	Contains the underlying GenAPI runtime software for the GigEVision, GenICamTL, and USB3Vision image acquisition interfaces.
<code>help</code>	The files in this directory act as the HALCON database, i.e., they provide information about HALCON to HDevelop and to all HALCON applications. In particular, they contain the operator database. The XML files starting with <code>index_manu</code> als contain the index data of the manuals. The XML files starting with <code>index_exam</code> ples contain the data for the Browse Examples dialog in HDevelop and those starting with <code>tip_of_the</code> _day contain the information for the Tip of the Day that appears in the HDevelop Start Dialog.
<code>include</code>	Contains the header files that are necessary to use HALCON within the programming languages C or C++.
<code>lib</code>	Contains the HALCON libraries.
<code>license</code>	The license file must be placed here (see <a href="#">section 3.1</a> on page 31).
<code>lut</code>	Contains predefined look-up tables.
<code>misc</code>	Contains miscellaneous files for the installer, e.g., the GigE Vision filter driver. In addition, the installer of the HALCON Variable Inspect can be found here. Please refer to the Programmer's Guide, <a href="#">section 3.3</a> on page 30, for more information about this extension.
<code>ocr</code>	Contains pretrained fonts.
<code>procedures</code>	Contains external procedures for HDevelop and HDevEngine.

### A.1.1.2 Linux

The default location for Linux is `/opt/halcon`:

<code>bin</code>	Contains HALCON programs, for example HDevelop, in subdirectories corresponding to the different platforms. The subdirectories <code>dotnet20</code> and <code>dotnet35</code> contain the HALCON/.NET assemblies based on .NET Framework 2.0, and .NET Framework 3.5, respectively.
<code>calib</code>	Contains description files for the calibration plates, which you can use to calibrate your camera.
<code>doc/html/manuals</code>	

Contains some of the User's Manuals.

`doc/html/reference/acquisition`

Contains the HTML documentation of the HALCON Image Acquisition Interfaces.

`doc/html/reference/io`

Contains the HTML documentation of the I/O device interfaces.

`doc/html/reference/operators`

Contains the HALCON Operator Reference.

`doc/index`

Contains the index files that are relevant for the full-text search of the documentation.

`doc/macros`

Contains the style files for the HALCON Operator Manual in all translated languages. These files set the layout and provide macros for names and formatting.

`doc/pdf/manuals`

Contains the PDF version of the User's Manuals.

`doc/pdf/reference`

Contains the PDF version of the HALCON Operator Reference in HDevelop syntax.

`doc/pdf/solution_guide`

Contains the PDF version of the [Solution Guide I](#), the Solution Guide II, and Solution Guide III.

`filter`

Contains predefined filter masks.

`genicam`

Contains the underlying GenAPI runtime software for the GigE Vision, GenI-CamTL, and USB3 Vision image acquisition interfaces.

<code>help</code>	The files in this directory act as the HALCON database, i.e., they provide information about HALCON to HDevelop and to all HALCON applications. In particular, they contain the operator database. The XML files starting with <code>index_manu</code> als contain the index data of the manuals. The XML files starting with <code>index_examples</code> contain the data for the Browse Examples dialog in HDevelop and those starting with <code>tip_of_the_day</code> contain the information for the Tip of the Day that appears in the HDevelop Start Dialog.
<code>include</code>	Contains the header files that are necessary to use HALCON within the programming languages C or C++.
<code>lib</code>	Contains the HALCON libraries and the libraries for the supported image acquisition interfaces.
<code>license</code>	The license file must be placed here (see <a href="#">section 3.1</a> on page 31).
<code>lut</code>	Contains predefined look-up tables.
<code>misc</code>	Contains miscellaneous files for the installer, e.g., the GigE Vision filter driver.
<code>ocr</code>	Contains pretrained fonts.
<code>procedures</code>	Contains external procedures for HDevelop and HDevEngine.

### A.1.1.3 macOS

HDevelop is located in /Applications.

The default location for macOS is /Library/Frameworks/HALCON.framework:

<code>calib</code>	Contains description files for the calibration plates, which you can use to calibrate your camera.
<code>filter</code>	Contains predefined filter masks.
<code>genicam</code>	Contains the underlying GenAPI runtime software for the GigEVision, GenI-CamTL, and USB3Vision image acquisition interfaces.
Headers	Contains the header files that are necessary to use HALCON within the programming languages C or C++.

- `help`

The files in this directory act as the HALCON database, i.e., they provide information about HALCON to HDevelop and to all HALCON applications. In particular, they contain the operator database. The XML files starting with `index_manu`als contain the index data of the manuals. The XML files starting with `index_examples` contain the data for the Browse Examples dialog in HDevelop and those starting with `tip_of_the_day` contain the information for the Tip of the Day that appears in the HDevelop Start Dialog.
- `lut`

Contains predefined look-up tables.
- `misc`

Contains miscellaneous files for the installer, e.g., the GigE Vision filter driver.
- `ocr`

Contains pretrained fonts.
- `procedures`

Contains external procedures for HDevelop and HDevEngine.

The following directories reside in `/Library/Application Support/HALCON-13.0`:

- `bin`

Contains some HALCON tools (`hcomp`, `hbench`, `hcheck_parallel`) and the `LicenseInstaller`.
- `doc/html/manuals`

Contains some of the User's Manuals.
- `doc/html/reference/acquisition`

Contains the HTML documentation of the HALCON Image Acquisition Interfaces.
- `doc/html/reference/io`

Contains the HTML documentation of the I/O device interfaces.
- `doc/html/reference/operators`

Contains the HALCON Operator Reference.
- `doc/index`

Contains the index files that are relevant for the full-text search of the documentation.
- `doc/macros`

Contains the style files for the HALCON Operator Manual in all translated languages. These files set the layout and provide macros for names and formatting.
- `doc/pdf/manuals`

Contains the PDF version of the User's Manuals.



<code>doc/pdf/reference</code>	Contains the PDF version of the HALCON Operator Reference in HDevelop syntax.
<code>doc/pdf/solution_guide</code>	Contains the PDF version of the <a href="#">Solution Guide I</a> , the Solution Guide II, and Solution Guide III.
<code>license</code>	The license file must be placed here (see <a href="#">section 3.1</a> on page 31).

Additionally, `/Library/Frameworks` contains the HALCON libraries. The corresponding directories reside in subdirectories, e.g., in `/Library/Frameworks/HALCONC++` for C++.

## A.1.2 Example Programs, Images, Models

The subdirectories of the directory designated by the environment variable `HALCONEXAMPLES` contain example programs for the different parts of the HALCON system. The default location is operating system-dependent:

Windows	<code>C:\Users\Public\Documents\MVTec\HALCON-13.0</code>
Linux	<code>/opt/halcon/examples</code>
macOS	<code>/Users/Shared/Library/Application Support/HALCON-13.0/examples</code>

If `%HALCONEXAMPLES%` is not set, `%HALCONROOT%\examples` will be used as a fallback.

- `3d_models`: This directory contains 3D object data used by the example programs.
- `c`: Examples for using HALCON within the programming language C (see also the Programmer's Guide, [chapter 23](#) on page 199).
- `c#`: Examples for using HALCON within the programming language C# (see also the Programmer's Guide, [section 17.1](#) on page 159).
- `cpp`: Examples for using HALCON within the programming language C++ (see also the Programmer's Guide, [chapter 13](#) on page 123).
- `cpp.net`: Examples for using HALCON within managed C++ (see also the Programmer's Guide, [section 17.1](#) on page 159).
- `delphi`: Examples for using HALCON within Borland Delphi.
- `extension_package`: The example user package `halconuser` (see also the [Extension Package Programmer's Manual](#)).
- `hdevelop`: Examples for using HALCON in HDevelop:
  - ▷ `Applications`: Examples that show how to realize machine vision applications.
  - ▷ `1D-Measuring...XLD`: Examples for the HALCON operators, in subdirectories following the operator hierarchy as in the HALCON Operator Reference or in HDevelop's menu `Operators`.

- **hdevengine:** Examples for using HDevEngine.
- **ia\_integration:** Example for an image acquisition interface (see also the [Image Acquisition Interface Programmer's Manual](#)).
- **images:** This directory contains example images and, in subdirectories, image sequences. These images are used by the example programs described above.
- **io\_integration:** Example for the integration of an I/O device interface.
- **solution\_guide:** Examples referenced in the [Solution Guide I](#), the [Solution Guide II](#), and the [Solution Guide III](#).
- **vb.net:** Examples for using HALCON within Visual Basic .NET (see also the Programmer's Guide, [section 17.1](#) on page 159).

To experiment with the examples without modifying the distributed versions, you can create a private copy in your own working directory. Note, however, that the .NET examples reference the HALCON/.NET assembly with a local path, thus after copying you must restore the reference (see the Programmer's Guide, [page 137](#)). You can also modify the environment variable HALCONEXAMPLES to point to the new location.

### A.1.3 Machine Configuration Data

The following directory contains machine-specific configuration data, e.g., results of the utility `hcheck_parallel` or the operator `optimize_aop`.

```
Windows  C:\ProgramData\MVTec\HALCON-13.0 (%ProgramData%...)
Linux    /opt/halcon ($HALCONROOT)
macOS    /Library/Frameworks/HALCON.framework
```

### A.1.4 User Configuration Data

The following directory contains user-specific configuration data, e.g., HDevelop preferences (`HDevelop.ini`).

```
Windows  C:\Users\%USERNAME%\AppData\Roaming\MVTec\HALCON-13.0 (%AppData%...)
Linux    $HOME/.hdevelop/MVTec
macOS    $HOME/Library/Preferences/com.mvtec.HDevelop.plist
```

In addition, the following directory is created by Windows 7 when the user copies files into the installation folder without administrator privileges:

```
Windows  C:\Users\%USERNAME%\AppData\Local\VirtualStore\Program Files\
          MVTec\HALCON-13.0 (%AppData%...)
```

## A.2 HALCON's Environment Variables

Most of the configuration necessary to work with HALCON amounts to setting environment variables, e.g., to tell HALCON the directories where to find images or extension packages etc. These environment variables are described below, after some information regarding the different platforms.

### A.2.1 Setting Environment Variables Under Windows

The installation program `setup.exe` automatically sets the necessary environment variables, e.g., `HALCONROOT`, `HALCONEXAMPLES`, `HALCONIMAGES`, and `PATH` (see below). To take a look at these settings, open the dialog `Start ▸ Settings ▸ Control Panel ▸ System (Windows Vista: ... ▸ System ▸ Advanced System Settings)` and select `Environment`. Under Windows 7/Windows 8, search for “Environment” using the system search, and select the search result “Edit the system environment variables” which appears in the category “Control Panel” (Windows 7) or “Settings” (Windows 8). You can add or modify a variable by entering the name of a variable and the desired value. If a value consists of multiple items, e.g., the variable `PATH`, which may contain multiple directories, those items must be separated by *semicolons*. Please note that in order to modify variables set during the HALCON installation you need administrator privileges!

### A.2.2 Setting Environment Variables Under Linux

As described in [section 2.2.2](#) on page 18, you must set the necessary environment variables in a login script or a shell resource script.

### A.2.3 HALCON-Specific Environment Variables

- `HALCONROOT`

This is the most important environment variable. It designates the directory where HALCON is installed. A typical path is, for example, `C:\Program Files\MVTec\HALCON` (Windows) or `/opt/halcon` (Linux).

If this variable is unset at the time `HDevelop` is run, or when the HALCON library is loaded, its value will be inferred from the path the executable or the library resides in, respectively. From this path the trailing part `bin\%HALCONARCH%` or `lib\%HALCONARCH%` will be removed. The variable `HALCONROOT` will then be set to the resulting path temporarily.

Based on this variable, the system switches to subdirectories, which are important for running HALCON. Some of them are listed below; the HALCON file structure is described in [section A.1](#) on page 43.

- `%HALCONROOT%\help`

The files in this directory act as the HALCON information database (see [section A.1](#) on page 43 for more information).

- `%HALCONROOT%\doc\html\reference\operators`

`HDevelop` expects the HTML files of the operator reference in this directory.

- %HALCONROOT%\license  
This directory contains the *license file* necessary for using HALCON (see [chapter 3](#) on page 31).
  - %HALCONROOT%\examples  
If the variable HALCONEXAMPLES (see below) is not set, the system looks for example programs in this directory.
  - %HALCONEXAMPLES%\images  
If the variable HALCONIMAGES (see below) is not set, the system looks for image files in this directory.
- HALCONEXAMPLES  
This environment variable designates the directory where HALCON example programs are installed.
  - HALCONIMAGES  
The system uses this environment variable to search for image files specified by a relative path. As a rule it contains several directory names, separated by semicolons (Windows) or colons (Linux).
  - HALCONARCH  
This variable designates the used platform. More details can be found in [section 1.3](#) on page 9.
  - HALCONEXTENSIONS  
This is a list of directories in which user-defined extension operators (so-called *extension packages*) are kept. Each package consists of a number of operators linked into a shared library, plus the additional operator documentation in help files and HTML files. See [section 2.13](#) on page 28 for information on how to install an extension package, and the [Extension Package Programmer's Manual](#) for details on creating your own extension packages.
  - HALCONSPY  
If this environment variable is defined (regardless of the value) *before you start* a HALCON program, the HALCON debugging tool *HALCON Spy* is activated. This corresponds to call the HALCON operator `set_spy` with the parameters "mode", "on" *within* a HALCON program. The main difference between the two modes for activating HALCON Spy is that by defining HALCONSPY it is possible to monitor an already linked HALCON program during runtime without modifications. For further information on how to use HALCON Spy and how to parameterize it via this environment variable please refer to the Programmer's Guide, [section 3.1](#) on page 29.
  - HALCON\_LICENSE\_FILE  
This environment variable can be set to the full path of a specific license file. In this case, the given license file is used and no further search is performed. Usually, the license file is searched in the current working directory and the installed `license` directory.

## A.2.4 General Environment Variables

- PATH  
**Windows:** During the installation, the directory %HALCONROOT%\bin\%HALCONARCH% is automatically added to the system variable PATH.

**Linux:** If you want to start HDevelop from an arbitrary directory, you must include the HALCON program path `$HALCONROOT/bin/$HALCONARCH` in the system variable `PATH`.

- `LD_LIBRARY_PATH` (Linux only)  
Please include the HALCON library path `$HALCONROOT/lib/$HALCONARCH` in the system variable `LD_LIBRARY_PATH`. This is necessary both for running HDevelop and for creating stand-alone applications.
- `DISPLAY` (Linux only)  
The system uses this environment variable to open windows. It is used in the same way as for other X applications.
- `HOME` (Linux only)  
This system variable points to your home directory.

## A.3 Registry Keys on Windows Systems

The Windows installer adds several keys to the system registry. The following sections list these registry keys. If multiple versions of HALCON are installed, version-specific information is stored under `HKLM\SOFTWARE\MVTec\HALCON\version`, where *version* is the major version number, e.g., 13.0.

Please note: On x64-based systems `HKLM\SOFTWARE\MVTec` has to be replaced by `HKLM\SOFTWARE\Wow6432Node\MVTec`.

### A.3.1 Registered File Types

```
HKCR\.hdev
HKCR\HDevelop.Source.File
HKCR\.dev
HKCR\.hdvp
HKCR\HDevelop.External.Procedure
HKCR\.dvp
HKCR\HDevelop.Procedure.Library
HKCR\.hdpl
HKCR\HALCON.Object
HKCR\.hobj
```

### A.3.2 Environment Variables

```
HKLM\SYSTEM\CurrentControlSet\Control\Session Manager\Environment\
HKLM\SYSTEM\CurrentControlSet\Control\Session Manager\Environment\HALCONARCH
HKLM\SYSTEM\CurrentControlSet\Control\Session Manager\Environment\HALCONEXAMPLES
HKLM\SYSTEM\CurrentControlSet\Control\Session Manager\Environment\HALCONIMAGES
HKLM\SYSTEM\CurrentControlSet\Control\Session Manager\Environment\HALCONROOT
HKLM\SYSTEM\CurrentControlSet\Control\Session Manager\Environment\PATH (modified)
```

### A.3.3 Basic Installation Data

```
HKLM\SOFTWARE\MVTec\HALCON\13.0\Initialized\InstallDir
HKLM\SOFTWARE\MVTec\HALCON\13.0\Initialized\ProgramGroup
HKLM\SOFTWARE\MVTec\HALCON\13.0\Initialized\Architecture
HKLM\SOFTWARE\MVTec\HALCON\13.0\Initialized\ExampleRoot
HKLM\SOFTWARE\MVTec\HALCON\13.0\Initialized\LanguageDoc
HKLM\SOFTWARE\MVTec\HALCON\13.0\Initialized\InstalledVersion
HKLM\SOFTWARE\MVTec\HALCON\13.0\Initialized\InstalledRevision
HKLM\SOFTWARE\MVTec\HALCON\13.0\Initialized\InstalledBuild
```

Sections selected during installation:

```
HKLM\SOFTWARE\MVTec\HALCON\13.0\InstalledComponents
```

(depending on the sections)

### A.3.4 Uninstall Information

```
HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall\MVTec HALCON 13.0\
InstallLocation
HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall\MVTec HALCON 13.0\
UninstallString
HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall\MVTec HALCON 13.0\
DisplayIcon
HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall\MVTec HALCON 13.0\
DisplayName
HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall\MVTec HALCON 13.0\
DisplayVersion
HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall\MVTec HALCON 13.0\
Publisher
HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall\MVTec HALCON 13.0\
Version
HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall\MVTec HALCON 13.0\
URLInfoAbout
HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall\MVTec HALCON 13.0\
URLUpdateInfo
HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall\MVTec HALCON 13.0\
NoModify
HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall\MVTec HALCON 13.0\
NoRepair
```

### A.3.5 HalconX

```
HKCR\HalconX.HBarCodeX
```

HKCR\HalconX.HBarrierX  
HKCR\HalconX.HBeadInspectionModelX  
HKCR\HalconX.HBgEstiX  
HKCR\HalconX.HCalibDataX  
HKCR\HalconX.HCameraSetupModelX  
HKCR\HalconX.HCamParX  
HKCR\HalconX.HClassBoxX  
HKCR\HalconX.HClassGmmX  
HKCR\HalconX.HClassKnnX  
HKCR\HalconX.HClassLUTX  
HKCR\HalconX.HClassMlpX  
HKCR\HalconX.HClassSvmX  
HKCR\HalconX.HClassTrainDataX  
HKCR\HalconX.HColorTransLUTX  
HKCR\HalconX.HComponentModelX  
HKCR\HalconX.HComponentTrainingX  
HKCR\HalconX.HComputeDeviceX  
HKCR\HalconX.HConditionX  
HKCR\HalconX.HDataCode2DX  
HKCR\HalconX.HDeformableModelX  
HKCR\HalconX.HDeformableSurfaceMatchingResultX  
HKCR\HalconX.HDeformableSurfaceModelX  
HKCR\HalconX.HDescriptorModelX  
HKCR\HalconX.HDevWindowStackX  
HKCR\HalconX.HDrawingObjectX  
HKCR\HalconX.HDualQuaternionX  
HKCR\HalconX.HEventX  
HKCR\HalconX.HFeatureSetX  
HKCR\HalconX.HFileX  
HKCR\HalconX.HFramegrabberX  
HKCR\HalconX.HFunction1DX  
HKCR\HalconX.HGnuplotX  
HKCR\HalconX.HHomMat2DX  
HKCR\HalconX.HHomMat3DX  
HKCR\HalconX.HImageX  
HKCR\HalconX.HInfoX  
HKCR\HalconX.HIOChannelX  
HKCR\HalconX.HIODeviceX  
HKCR\HalconX.HLexiconX  
HKCR\HalconX.HMatrixX  
HKCR\HalconX.HMeasureX  
HKCR\HalconX.HMessageQueueX  
HKCR\HalconX.HMessageX  
HKCR\HalconX.HMetrologyModelX  
HKCR\HalconX.HMiscX  
HKCR\HalconX.HMutexX  
HKCR\HalconX.HNCCModelX

HKCR\HalconX.HObjectModel3DX  
HKCR\HalconX.HOCRBoxX  
HKCR\HalconX.HOCRCnnX  
HKCR\HalconX.HOCRKnnX  
HKCR\HalconX.HOCRMlpX  
HKCR\HalconX.HOCRSvmX  
HKCR\HalconX.HOCVX  
HKCR\HalconX.HOperatorSetX  
HKCR\HalconX.HPoseX  
HKCR\HalconX.HQuaternionX  
HKCR\HalconX.HRegionX  
HKCR\HalconX.HSampleIdentifierX  
HKCR\HalconX.HScatteredDataInterpolatorX  
HKCR\HalconX.HScene3DX  
HKCR\HalconX.HSerializedItemX  
HKCR\HalconX.HSerialX  
HKCR\HalconX.HShapeModel3DX  
HKCR\HalconX.HShapeModelX  
HKCR\HalconX.HSheetOfLightModelX  
HKCR\HalconX.HSocketX  
HKCR\HalconX.HStereoModelX  
HKCR\HalconX.HSurfaceMatchingResultX  
HKCR\HalconX.HSurfaceModelX  
HKCR\HalconX.HSystemX  
HKCR\HalconX.HTemplateX  
HKCR\HalconX.HTextModelX  
HKCR\HalconX.HTextResultX  
HKCR\HalconX.HTextureInspectionModelX  
HKCR\HalconX.HTextureInspectionResultX  
HKCR\HalconX.HTupleX  
HKCR\HalconX.HUntypedObjectX  
HKCR\HalconX.HVariationModelX  
HKCR\HalconX.HWindowX  
HKCR\HalconX.HWindowXCtrl  
HKCR\HalconX.HXLDContX  
HKCR\HalconX.HXLDDistTransX  
HKCR\HalconX.HXLDExtParaX  
HKCR\HalconX.HXLDModParaX  
HKCR\HalconX.HXLDParaX  
HKCR\HalconX.HXLDPolyX  
HKCR\HalconX.HXLDX

### A.3.6 HDevEngineXLib

HKCR\HDevEngineXLib.HDevEngineX  
HKCR\HDevEngineXLib.HDevProgramX



```
HKCR\HDevEngineXLib.HDevProgramCallX  
HKCR\HDevEngineXLib.HDevProcedureX  
HKCR\HDevEngineXLib.HDevProcedureCallX  
HKCR\HDevEngineXLib.HDevOperatorImplX
```



# Index

- compatibility (HALCON), 8
- customize HALCON installation, 23
- development license, 33
- development version, 7
- DISPLAY (environment variable), 53
- environment variables (general), 52
- environment variables (HALCON), 51
- evaluation license, 33
- examples (HALCON directory), 49
- get host ID manually, 32
- get host ID of network card, 34
- get required HALCON modules, 34
- HALCON\_LICENSE\_FILE (environment variable), 52
- HALCONARCH (environment variable), 52
- HALCONEXAMPLES (environment variable), 52
- HALCONEXTENSIONS (environment variable), 52
- HALCONIMAGES (environment variable), 52
- HALCONROOT (environment variable), 51
- HALCONSPY (environment variable), 52
- hhostid, 32, 40
- HOME (environment variable), 53
- images (HALCON directory), 50
- install additional HALCON parts, 21
- install extension package, 28
- install HALCON, 13
- install HALCON for the first time, 14
- install image acquisition interface, 28
- install runtime version, 21
- install runtime version (silent), 17
- installation troubleshooting, 37
- installed file structure, 43
- LD\_LIBRARY\_PATH (environment variable), 53
- license, 31
  - overview, 10
- license file, 31
- licensing troubleshooting, 39
- maintenance release, 8
- nodelocked development license bound to dongle, 34
- nodelocked development license bound to network card, 34
- PATH (environment variable), 52
- register halconx.dll (HALCON/COM), 37
- runtime license, 34
- runtime version, 7
- set environment variables
  - Linux, 51
  - Windows, 51
- switch between HALCON platform versions, 28
- switch between HALCON versions, 27
- system requirements, 9
- troubleshooting (miscellaneous), 40
- troubleshooting for get host ID, 40
- uninstall HALCON, 24
- uninstallation troubleshooting, 38
- unregister halconx.dll (HALCON/COM), 38
- update HALCON, 23
- upgrade HALCON, 23
- upgrade license, 36
- version (HALCON), 8
- WOW64, 10